



Instituto Tecnológico de Salina Cruz

Fundamentos de Redes

Semestre Enero – Julio 2015

Reporte de Practica

Practica nº 1

Unidad 6

Nombre: Jesus Alberto Alvarez Camera

Fecha: 06 de junio del 2015

Objetivos:

- Conectar una red de acuerdo con el Diagrama de topología
- Realizar tareas de configuración básicas en un router
- Configurar y activar interfaces
- Configurar el enrutamiento OSPF en todos los routers
- Configurar las ID del router OSPF
- Verificar el enrutamiento OSPF por medio de los comandos show
- Configurar una ruta estática por defecto

Instrucciones:

- 1.- Realizar la tabla de ruteo.
- 2.- Realizar configuraciones iniciales.
- 3.- Identificar comandos a utilizar.
- 4.- Verificar configuraciones mediante protocolo OSPF

Materiales:

- Computadoras.
- Cisco Packet Tracer.
- Silla.

Escenario.





Tabla de direccionamiento.

Dispositivo	Interfaz	Dirección IP	Máscara de subred	Gateway por defecto
R1	Fa0/0	172.16.1.17	255.255.255.240	No aplicable
	S0/0/0	192.168.10.1	255.255.255.252	No aplicable
	S0/0/1	192.168.10.5	255.255.255.252	No aplicable
R2	Fa0/0	10.10.10.1	255.255.255.0	No aplicable
	S0/0/0	192.168.10.2	255.255.255.252	No aplicable
	S0/0/1	192.168.10.9	255.255.255.252	No aplicable
R3	Fa0/0	172.16.1.33	255.255.255.248	No aplicable
	S0/0/0	192.168.10.6	255.255.255.252	No aplicable
	S0/0/1	192.168.10.10	255.255.255.252	No aplicable
PC1	NIC	172.16.1.20	255.255.255.240	172.16.1.17
PC2	NIC	10.10.10.10	255.255.255.0	10.10.10.1
PC3	NIC	172.16.1.35	255.255.255.248	172.16.1.33

A continuación se establecen las configuraciones básicas de los Routers, como son el cambio de contraseña, el cambio de nombre y la asignación de un banner de la siguiente manera.

Router 1 cambio de nombre (computadora)



```
Physical Config CLI
IOS Command Line Interface
PT 1001 (PTSC2005) processor (revision 0x200) with 60416K/5120K bytes of memory
-
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname computadora
computadora(config)#
```

Copy Paste

Asignando contraseña al router 1



```
Physical Config CLI
IOS Command Line Interface
-
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname computadora
computadora(config)#enable password computadora
computadora(config)#
```

Copy Paste

Asignando un banner de bienvenida al router 1

```
Physical Config CLI
IOS Command Line Interface
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname computadora
computadora(config)#enable password computadora
computadora(config)#banner motd #jesus alberto alvarez camera - redes de computa
doras 2#^Z
computadora#
%SYS-5-CONFIG_I: Configured from console by console
^Z
computadora#
```

Copy Paste

Router 2 cambio de nombre (redes)

```
Physical Config CLI
IOS Command Line Interface
PT 1001 (PTSC2005) processor (revision 0x200) with 60416K/5120K bytes of memory
.
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---
Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname redes
redes(config)#
```

Copy Paste

Asignando contraseña al router 2

Physical Config CLI

IOS Command Line Interface

```
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname redes
redes(config)#enable password redes
redes(config)#
```

Copy Paste

Asignando un banner de bienvenida al router 2

Physical Config CLI

IOS Command Line Interface

```
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname redes
redes(config)#enable password redes
redes(config)#banner motd #jesus lberto alvarez camera - redes de computadoras 2
#^Z
redes#
%SYS-5-CONFIG_I: Configured from console by console
^Z
redes#
```

Copy Paste

Router 3 cambio de nombre (redes)

Physical Config CLI

IOS Command Line Interface

```
PT 1001 (PTSC2005) processor (revision 0x200) with 60416K/5120K bytes of memory
-
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname unidad2
unidad2(config)#
```

Copy Paste

Asignando contraseña al router 3

Physical Config CLI

IOS Command Line Interface

```
-
Processor board ID PT0123 (0123)
PT2005 processor: part number 0, mask 01
Bridging software.
X.25 software, Version 3.0.0.
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf ter
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname unidad2
unidad2(config)#enable password unidad2
unidad2(config)#
```

Copy Paste

Asignando un banner de bienvenida al router 3

```
Physical Config CLI
IOS Command Line Interface
4 FastEthernet/IEEE 802.3 interface(s)
2 Low-speed serial(sync/async) network interface(s)
32K bytes of non-volatile configuration memory.
63488K bytes of ATA CompactFlash (Read/Write)

--- System Configuration Dialog ---

Continue with configuration dialog? [yes/no]: n

Press RETURN to get started!

Router>enable
Router#conf tex
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname unidad2
unidad2(config)#enable password unidad2
unidad2(config)#banner motd #jesus alberto alvarez camera - redes de computadora
s 2#^Z
unidad2#
%SYS-5-CONFIG_I: Configured from console by console
^Z
unidad2#
```

Copy Paste

A continuación se configuraran los puertos seriales y fastethernet de cada uno de los Routers.

Configuración de puertos seriales del router 1

```
Dreysi>enable
Password:
Dreysi#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Dreysi(config)#interface fa0/0
Dreysi(config-if)#ip address 172.16.1.17 255.255.255.240
Dreysi(config-if)#no shut

-----
Dreysi(config)#interface s2/0
Dreysi(config-if)#ip address 192.168.10.1 255.255.255.252
Dreysi(config-if)#no shut

%LINK-5-CHANGED: Interface Serial2/0, changed state to down
Dreysi(config-if)#

Dreysi(config)#interface s3/0
Dreysi(config-if)#ip address 192.168.10.5 255.255.255.252
Dreysi(config-if)#no shut

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Dreysi(config-if)#
```

Configuración de puertos seriales del router 2

```
banner motd

Chuleta>enable
Password:
Chuleta#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Chuleta(config)#interface fa0/0
Chuleta(config-if)#ip address 10.10.10.1 255.0.0.0
Chuleta(config-if)#no shut

Chuleta(config)#interface s2/0
Chuleta(config-if)#ip address 192.168.10.2 255.255.255.252
Chuleta(config-if)#no shut

Chuleta(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Chuleta(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Chuleta(config)#interface s3/0
Chuleta(config-if)#ip address 192.168.10.9 255.255.255.252
Chuleta(config-if)#no shut

%LINK-5-CHANGED: Interface Serial3/0, changed state to down
Chuleta(config-if)#
Chuleta(config-if)#
```

Configuración de puertos seriales del router 3

```
eduardo salazar irrizari unidad 6

banner motd

Crossas>enable
Password:
Crossas#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
Crossas(config)#interface f0/0
Crossas(config-if)#ip address 172.16.1.33 255.255.255.248
Crossas(config-if)#no shut

Crossas(config)#interface s2/0
Crossas(config-if)#ip address 192.168.10.6 255.255.255.252
Crossas(config-if)#no shut

Crossas(config)#interface s3/0
Crossas(config-if)#ip address 192.168.10.10 255.255.255.252
Crossas(config-if)#no shut

Crossas(config-if)#
%LINK-5-CHANGED: Interface Serial3/0, changed state to up
```

A continuación se verificara el direccionamiento ip y las interfaces en cada uno de los Routers.

Router 1

```
ingenieria en TICS
banner motd

Dreysi>enable
Password:
Dreysi#show ip brief

% Invalid input detected at '^' marker.

Dreysi#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol

FastEthernet0/0          172.16.1.17     YES manual up           up
FastEthernet1/0          unassigned      YES unset  administratively down down
Serial2/0                 192.168.10.1    YES manual up           up
Serial3/0                 192.168.10.6    YES manual up           up
FastEthernet4/0          unassigned      YES unset  administratively down down
FastEthernet5/0          unassigned      YES unset  administratively down down
```

Router 2

```
Bienvenido a la materia de redes eduardo salazar

banner motd

Chuleta>enable
Password:
Chuleta#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol

FastEthernet0/0          10.10.10.1      YES manual up           up
FastEthernet1/0          unassigned      YES unset  administratively down down
Serial2/0                 192.168.10.2    YES manual up           up
Serial3/0                 192.168.10.9    YES manual up           up
FastEthernet4/0          unassigned      YES unset  administratively down down
FastEthernet5/0          unassigned      YES unset  administratively down down
```

Router 3

```
eduardo salazar irrizeri unidad 6


banner motd

Crossas>enable
Password:
Crossas#show ip interface brief
Interface                IP-Address      OK? Method Status      Protocol

FastEthernet0/0          172.16.1.33     YES manual up           up
FastEthernet1/0          unassigned      YES unset  administratively down down
Serial2/0                 192.168.10.6    YES manual up           up
Serial3/0                 192.168.10.10   YES manual up           up
FastEthernet4/0          unassigned      YES unset  administratively down down
FastEthernet5/0          unassigned      YES unset  administratively down down
```


Como siguiente punto se Configuraran las interfaces Ethernet de las PCs de la siguiente manera

Pc1.




The screenshot shows the 'IP Configuration' window for PC1. The window title is 'IP Configuration' with a close button (X). The 'IP Configuration' section has two radio buttons: 'DHCP' (unselected) and 'Static' (selected). Below this, there are four text input fields: 'IP Address' with the value '172.16.1.20', 'Subnet Mask' with '255.255.255.240', 'Default Gateway' with '172.16.1.17', and 'DNS Server' which is empty. To the right of the configuration window is a vertical toolbar with a 'Web Browser' icon (a globe with 'http:') and a computer monitor icon.

Pc2.



The screenshot shows the 'IP Configuration' window for PC2. The window title is 'IP Configuration' with a close button (X). The 'IP Configuration' section has two radio buttons: 'DHCP' (unselected) and 'Static' (selected). Below this, there are four text input fields: 'IP Address' with the value '10.10.10.10', 'Subnet Mask' with '255.0.0.0', 'Default Gateway' with '10.10.10.1', and 'DNS Server' which is empty. To the right of the configuration window is a vertical toolbar with a 'Web Browser' icon (a globe with 'http:') and a computer monitor icon.

Pc3.



The screenshot shows the 'IP Configuration' window for PC3. The window title is 'IP Configuration' with a close button (X). The 'IP Configuration' section has two radio buttons: 'DHCP' (unselected) and 'Static' (selected). Below this, there are four text input fields: 'IP Address' with the value '172.16.1.35', 'Subnet Mask' with '255.255.255.248', 'Default Gateway' with '172.16.1.33', and 'DNS Server' which is empty. To the right of the configuration window is a vertical toolbar with a 'Web Browser' icon (a globe with 'http:') and a computer monitor icon.

A continuación se Probara la configuración de la PC ejecutando un ping desde la PC al gateway por defecto.

Ping desde la PC1 al Gateway por defecto.

```
Physical Config Desktop Software/Services
Command Prompt
Packet Tracer PC Command Line 1.0
PC>ping 172.16.1.17

Pinging 172.16.1.17 with 32 bytes of data:

Reply from 172.16.1.17: bytes=32 time=1ms TTL=255
Reply from 172.16.1.17: bytes=32 time=0ms TTL=255
Reply from 172.16.1.17: bytes=32 time=0ms TTL=255
Reply from 172.16.1.17: bytes=32 time=1ms TTL=255

Ping statistics for 172.16.1.17:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 1ms, Average = 0ms

PC>
```

Como siguiente paso se observa la configuracion de OSPF en cada uno de los routers

Router 1

```
Dreysi>enable
Password:
Dreysi#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Dreysi(config)#router ospf 1
Dreysi(config-router)#network 172.16.1.16 0.0.0.15 area 0
Dreysi(config-router)#network 192.168.10.4 0.0.0.3 area 0
Dreysi(config-router)#network 192.168.10.0 0.0.0.3 area 0
Dreysi(config-router)#end
Dreysi#
%SYS-5-CONFIG_I: Configured from console by console
```

Router 2

```
Chuleta>enable
Password:
Chuleta#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Chuleta(config)#router ospf 1
Chuleta(config-router)#network 10.10.10.0 0.0.0.255 area 0
Chuleta(config-router)#network 192.168.10.0 0.0.0.3 area 0
Chuleta(config-router)#
01:03:03: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.5 on Serial2/0 from LOADING
to FULL, Loading Done

Chuleta(config-router)#network 192.168.10.8 0.0.0.3 area 0
% Invalid input detected at '^' marker.

Chuleta(config-router)#network 192.168.10.8 0.0.0.3 area 0
Chuleta(config-router)#end
Chuleta#
%SYS-5-CONFIG_I: Configured from console by console
```

Router 3

```
Crosas>enable
Password:
Crosas#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Crosas(config)#router ospf 1
Crosas(config-router)#network 172.16.1.32 0.0.0.7 area 0
Crosas(config-router)#network 192.168.10.4 0.0.0.3 area 0
Crosas(config-router)#
01:06:02: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.5 on Serial12/0 from LOADING
to FULL, Loading Done
Crosas(config-router)#network 192.168.10.8 0.0.0.3 area 0
Crosas(config-router)#
01:06:41: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.9 on Serial12/0 from LOADING
to FULL, Loading Done
Crosas(config-router)#end
Crosas#
%SYS-5-CONFIG_I: Configured from console by console
```

Examinar las ID actuales del router en la topología.

1.- ¿Cuál es la ID del router en R1?

192.168.10.5

2.- ¿Cuál es la ID del router en R2?

192.168.10.9

3.- ¿Cuál es la ID del router en R3?

192.168.10.10

A continuación se Utilizaran las direcciones de loopback para cambiar las ID del router de los routers en la topología.

```
Dreysi(config)#interface loopback 0
Dreysi(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
Dreysi(config-if)#ip address 10.1.1.1 255.255.255.255

Chuleta(config)#interface loopback 0
Chuleta(config-if)#ip address 11.2.2.2 255.255.255.255
Chuleta(config-if)#end
Chuleta#
%SYS-5-CONFIG_I: Configured from console by console

Crosas(config)#interface loopback 0
Crosas(config-if)#
%LINK-5-CHANGED: Interface Loopback0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up
Crosas(config-if)#ip address 10.3.3.3 255.255.255.255
Crosas(config-if)#end
Crosas#
```

Como siguiente punto Utilizar el comando show ip ospf neighbors para verificar que se han cambiado las ID de los routers.

Router 1

```
Dreysi#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.10.9	0	FULL/ -	00:00:30	192.168.10.2	Serial2/0
192.168.10.10	0	FULL/ -	00:00:37	192.168.10.6	Serial3/0

Router 2

```
Chuleta#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.10.5	0	FULL/ -	00:00:36	192.168.10.1	Serial2/0
192.168.10.10	0	FULL/ -	00:00:35	192.168.10.10	Serial3/0

Router 3

```
Crosas#show ip ospf neighbor
```

Neighbor ID	Pri	State	Dead Time	Address	Interface
192.168.10.9	0	FULL/ -	00:00:38	192.168.10.9	Serial3/0
192.168.10.5	0	FULL/ -	00:00:34	192.168.10.5	Serial2/0

Utilizar el comando router-id para cambiar el ID del router en el router 1.

```
Dreysi>enable
Password:
Dreysi#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Dreysi(config)#router ospf 1
Dreysi(config-router)#router-id 10.4.4.4
Dreysi(config-router)#Reload or use "clear ip ospf process" command, for this to
take effect

Dreysi(config-router)#end
Dreysi#
%SYS-5-CONFIG_I: Configured from console by console

Dreysi#clear ip ospf process
Reset ALL OSPF processes? [no]: yes

Dreysi#
00:17:07: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.9 on Serial2/0 from FULL to
DOWN. Neighbor Down: Adjacency forced to reset
```

En el router R1 utilice el comando show ip protocols para ver información sobre las operaciones del protocolo de enrutamiento.

```
ingenieria en TICs
banner motd
Dreysi#enable
Dreysi#show ip protocols
```

Routing Protocol is "ospf 1"

Outgoing update filter list for all interfaces is not set

Incoming update filter list for all interfaces is not set

Router ID 10.4.4.4

Number of areas in this router is 1. 1 normal 0 stub 0 nssa

Maximum path: 4

Routing for Networks:

172.16.1.16	0.0.0.15	area 0
192.168.10.4	0.0.0.3	area 0
192.168.10.0	0.0.0.3	area 0

Routing Information Sources:

Gateway	Distance	Last Update
10.4.4.4	110	00:01:32
192.168.10.5	110	00:09:42
192.168.10.9	110	00:01:32
192.168.10.10	110	00:01:32

Distance: (default is 110)

Visualice la tabla de enrutamiento en el router R1. En la tabla de enrutamiento las rutas OSPF se indican con una "O".

```
Dreysi#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

    10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
O       10.0.0.0/8 [110/65] via 192.168.10.2, 00:04:10, Serial2/0
C       10.1.1.1/32 is directly connected, Loopback0
    172.16.0.0/16 is variably subnetted, 2 subnets, 2 masks
C       172.16.1.16/28 is directly connected, FastEthernet0/0
O       172.16.1.32/29 [110/65] via 192.168.10.6, 00:04:10, Serial3/0
    192.168.10.0/30 is subnetted, 3 subnets
C       192.168.10.0 is directly connected, Serial2/0
C       192.168.10.4 is directly connected, Serial3/0
O       192.168.10.8 [110/128] via 192.168.10.6, 00:04:10, Serial3/0
        [110/128] via 192.168.10.2, 00:04:10, Serial2/0
```

Utilizar el comando show interfaces serial0/0/0 en el router 1 para visualizar el ancho de banda de la interfaz Serial 0/0/0.

```
Dreysi#show interface serial2/0
Serial2/0 is up, line protocol is up (connected)
Hardware is HD64570
Internet address is 10.1.1.1/30
MTU 1500 bytes, BW 128 kbit, DLY 20000 usec,
reliability 100%, txload 1/255, rxload 1/255
Encapsulation HDLC, loopback not set, keepalive set (10 sec)
Last input never, output never, output hang never
Last clearing of "show interface" counters never
Input queue: 0/75/0 (size/max/drops); Total output drops: 0
Queueing strategy: weighted fair
Output queue: 0/1000/64/0 (size/max total/threshold/drops)
Conversations 0/0/256 (active/max active/max total)
Reserved Conversations 0/0 (allocated/max allocated)
Available Bandwidth 36 kilobits/sec
5 minute input rate 54 bits/sec, 0 packets/sec
5 minute output rate 54 bits/sec, 0 packets/sec
 173 packets input, 12496 bytes, 0 no buffer
Received 0 broadcasts, 0 runts, 0 giants, 0 throttles
 0 input errors, 0 CRC, 0 frame, 0 overrun, 0 ignored, 0 abort
 140 packets output, 9620 bytes, 0 underruns
 0 output errors, 0 collisions, 1 interface resets
 0 output buffer failures, 0 output buffers swapped out
```

Utilizar el comando bandwidth para cambiar el ancho de banda de las interfaces seriales de los Routers 1 y Router 2 al ancho de banda actual, 64 kbps.

```
Dreysi(config)#interface serial2/0
Dreysi(config-if)#bandwidth 64
Dreysi(config-if)#interface serial3/0
Dreysi(config-if)#bandwidth 64

Chulata(config)#interface serial2/0
Chulata(config-if)#bandwidth 64
Chulata(config-if)#interface serial3/0
Chulata(config-if)#bandwidth 64
```

Utilizar el comando show ip ospf interface en el router R1 para verificar el costo de los enlaces seriales. El costo de cada uno de los enlaces seriales ahora es de 1562, el resultado del cálculo: 108/64.000 bps.

```
Serial3/0 is up, line protocol is up
Internet address is 192.168.10.5/30, Area 0
Process ID 1, Router ID 10.4.4.4, Network Type POINT-TO-POINT, Cost: 1562
Transmit Delay is 1 sec, State POINT-TO-POINT, Priority 0
No designated router on this network
No backup designated router on this network
Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
Hello due in 00:00:02
Index 2/2, flood queue length 0
Next 0x0(0)/0x0(0)
Last flood scan length is 1, maximum is 1
Last flood scan time is 0 msec, maximum is 0 msec
Neighbor Count is 1, Adjacent neighbor count is 1
Adjacent with neighbor 192.168.10.10
Suppress hello for 0 neighbor(s)
Serial2/0 is up, line protocol is up
Internet address is 192.168.10.1/30, Area 0
Process ID 1, Router ID 10.4.4.4, Network Type POINT-TO-POINT, Cost: 1562
Transmit Delay is 1 sec, State POINT-TO-POINT, Priority 0
No designated router on this network
No backup designated router on this network
Timer intervals configured, Hello 10, Dead 40, Wait 40, Retransmit 5
Hello due in 00:00:03
```

Configurar una dirección de loopback en el router 1 para simular un enlace a un ISP.

```
Dreysi(config)#interface loopback 1
Dreysi(config-if)#
%LINK-5-CHANGED: Interface Loopback1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback1, changed state to up
Dreysi(config-if)#ip address 172.30.1.1 255.255.255.252
```

Configurar los intervalos de Hello y Dead de OSPF.

```
Dreysi(config)#interface serial2/0
Dreysi(config-if)#ip ospf hello-interval 5
Dreysi(config-if)#ip ospf dead-interval 20
Dreysi(config-if)#
01:56:43: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.9 on Serial2/0 from FULL to
DOWN, Neighbor Down: Dead timer expired

01:56:43: %OSPF-5-ADJCHG: Process 1, Nbr 192.168.10.9 on Serial2/0 from FULL to
DOWN, Neighbor Down: Interface down or detached

-----
Chuleta(config)#interface serial2/0
Chuleta(config-if)#ip ospf hello-interval 5
Chuleta(config-if)#ip ospf dead-interval 20
Chuleta(config-if)#
03:23:05: %OSPF-5-ADJCHG: Process 1, Nbr 10.4.4.4 on Serial2/0 from LOADING to F
ULL, Loading Done
```

Utilizar el comando show ip ospf interface serial0/0/0 para verificar que se han cambiado los intervalos del temporizador Hello y del temporizador Dead.

```
Chuleta#show ip ospf interface serial2/0
Serial2/0 is up, line protocol is up
Internet address is 192.168.10.2/30, Area 0
Process ID 1, Router ID 192.168.10.9, Network Type POINT-TO-POINT, Cost: 1562
Transmit Delay is 1 sec, State POINT-TO-POINT, Priority 0
No designated router on this network
No backup designated router
Timer intervals configured, Hello 5, Dead 20, Wait 20, Retransmit 5
Hello due in 00:00:02
Index 2/2, flood queue length 0
Next 0x0(0)/0x0(0)
Last flood scan length is 1, maximum is 1
Last flood scan time is 0 msec, maximum is 0 msec
Neighbor Count is 1, Adjacent neighbor count is 1
Adjacent with neighbor 10.4.4.4
Suppress hello for 0 neighbor(s)
```

Utilizar el comando show ip ospf neighbor en el router R1 para verificar que la adyacencia vecina con R2 se ha restaurado.

```
Dreysi#show ip ospf neighbor
Neighbor ID      Pri   State           Dead Time   Address      Interface
192.168.10.9    0    FULL/ -         00:00:16   192.168.10.2 Serial2/0
192.168.10.10   0    FULL/ -         00:00:31   192.168.10.6 Serial3/0
Dreysi#
```

Conclusión

En esta práctica se aprendió a configurar un router desde su cambio de nombre hasta la colocación de un banner de bienvenida, pasando por la colocación de una contraseña. Una vez realizado esto se procedió a configurar los puertos seriales y los fastethernet de cada uno de ellos así como las direcciones IP de cada una de las pcs y como parte final se utilizaron los comandos cisco para establecer los temporizadores hello y dead.